


## Beyond 2020 Tip Sheet

After you open the table in B2020 you will see the following:



Mobility 5	Total - Mother tongue	English	French	Non-official language	English and French	English and non-official la...	French and non-official langu...	English and French and non-official language
Total - Mobility status 5 years ago	1,070	830	100	140	0	0	0	0
Non-movers	710	545	90	75	0	0	0	0
Movers	360	285	10	65	0	0	0	0
Non-migrants	115	95	15	15	0	0	0	0
Migrants	240	190	0	50	0	0	0	0
Internal migrants	205	160	0	40	0	0	0	0
Intraprovincial migrants	140	120	0	15	0	0	0	0
Interprovincial migrants	70	45	0	20	0	0	0	0
External migrants	40	30	0	10	0	0	0	0

Please note that all of the data is there. However, Dimensions can be displayed in a dimension tile or along the columns or rows of a table view. Dimensions are an aspect of the data (such as Mobility Status), which is broken down into one or more items (such as non-movers or Migrants).

The toolbar consists of the Active Dimension Box, the Previous Item and Next Item buttons, and the toolbar buttons.

The Active Dimension Box identifies the dimension that is currently selected (in this table view - Mobility Status). To set the active dimension, select the desired dimension from the drop-down list box. For example, the table view is showing data for Denman Island Trust Area. You can select the Geography Dimension from the drop-down list box then use the “Next Item” or “Previous Item” buttons to either side of the box to switch to a new geography.

The following image shows the table view after I have done this task. The table view appears the same as before except that the data is now for Hornby Island Trust Area.

Geography: Hornby Island Trust Area

Mobility 5	Total - Mother tongue	English	French	Non-official language	English and French	English and non-official la...	French and non-official langu...	English and French and
Total - Mobility status 5 years ago	1,050	905	40	100	0	0	0	
Non-movers	810	700	30	80	0	0	0	
Movers	240	210	15	20	0	0	0	
Non-migrants	95	75	15	0	0	0	0	
Migrants	150	135	0	10	0	0	0	
Internal migrants	145	135	0	15	0	0	0	
Intraprovincial migrants	120	115	0	0	0	0	0	
Interprovincial migrants	25	20	0	10	0	0	0	
External migrants	0	0	0	0	0	0	0	

The following Dimensions are along the columns or rows of the table view: Mobility Status (rows) and Mother Tongue (columns).

The following Dimensions are displayed in the dimension tile: Geography, Age Groups and Sex.

## Switching Dimensions

Switching dimensions involves dragging a dimension tile from the dimension bar into the table, or dragging a heading from the column or row dimension areas into the dimension bar. When the tile or heading is dropped, the two dimensions change places. You can also switch column and row dimensions.

To switch dimensions:

1. Select the dimension you want to move.
2. Do one of the following:
  - Drag and drop the tile on the row headings if you want to replace the row dimension.
  - Drag and drop the tile on the column headings if you want to replace the column dimension.

- Drag and drop the tile on a dimension in the dimension bar if you want to replace one of the dimensions in the dimension bar.

The following is an image after I have switched the Mobility Dimension with the Age Group Dimension.

Mother tongue	Total - Mother tongue	English	French	Non-official language	English and French	English and non-official language	French and non-official language	English, French and non-official language
Total - Age groups	1,070	830	100	140	0	0	0	0
5 to 9 years	50	25	15	10	0	0	0	0
10 to 14 years	80	40	30	0	0	0	0	0
15 to 19 years	65	45	0	20	0	0	0	0
20 to 24 years	35	35	0	0	0	0	0	0
25 to 29 years	30	15	0	15	0	0	0	0
30 to 34 years	40	35	0	0	0	0	0	0
35 to 39 years	75	45	15	15	0	0	0	0
40 to 44 years	85	50	30	10	0	0	0	0
45 to 49 years	70	60	10	0	0	0	0	0
50 to 54 years	95	75	0	20	0	0	0	0
55 to 59 years	150	145	0	10	0	0	0	0
60 to 64 years	130	120	0	10	0	0	0	0
65 to 69 years	65	55	0	15	0	0	0	0
70 to 74 years	60	50	0	10	0	0	0	0
75 years and over	45	45	0	0	0	0	0	0

## Nesting Dimensions

Nesting lets you display more than one dimension along the columns or rows. It involves positioning a dimension tile over the border of existing headings in the column or row dimension. When the tile is released, new headings are added to the column or row areas.

To nest dimensions:

1. In the dimension bar, select the dimension you want to nest.
2. Do one of the following:
  - To nest along the rows, drag and drop the dimension tile onto the outer or inner border of the row headings.
  - To nest along the columns, drag and drop the dimension tile onto the top or bottom of the border of the column headings.

The dimension tile is ready to be dropped when the border of the row or column headings you are nesting into becomes highlighted.

The following is an image after I have nested the Mobility Dimension under the Age Group Dimension.

Age groups		Mother tongue	Total - Mother tongue	English	French	Non-official language	English and French	English and non-official la...	Franc...
Total - Age groups	Total - Mobility status 5 years ago		1,070	830	100	140	0	0	
	Non-movers		710	545	90	75	0	0	
	Movers		360	285	10	65	0	0	
	Non-migrants		115	95	15	15	0	0	
	Migrants		240	190	0	50	0	0	
	Internal migrants		205	160	0	40	0	0	
	Intraprovincial migrants		140	120	0	15	0	0	
	Interprovincial migrants		70	45	0	20	0	0	
	External migrants		40	30	0	10	0	0	
5 to 9 years	Total - Mobility status 5 years ago		50	25	15	10	0	0	
	Non-movers		40	15	15	10	0	0	
	Movers		0	0	0	0	0	0	
	Non-migrants		0	0	0	0	0	0	
	Migrants		0	0	0	0	0	0	
	Internal migrants		0	0	0	0	0	0	
	Intraprovincial migrants		0	0	0	0	0	0	
	Interprovincial migrants		0	0	0	0	0	0	
	External migrants		0	10	0	0	0	0	
10 to 14 years	Total - Mobility status 5 years ago		80	40	30	0	0	0	
	Non-movers		50	15	30	0	0	0	
	Movers		30	30	0	0	0	0	
	Non-migrants		25	25	0	0	0	0	
	Migrants		10	10	0	0	0	0	
	Internal migrants		0	10	0	0	0	0	
	Intraprovincial migrants		0	10	0	0	0	0	
	Interprovincial migrants		0	0	0	0	0	0	
	External migrants		0	0	0	0	0	0	
15 to 19 years	Total - Mobility status 5 years ago		65	45	0	20	0	0	

The following is an image after I have nested the Sex Dimension under Mother Tongue Dimension.

Beyond 20/20 Professional Browser - [Population Aged 5 Years and Over by Mobility Status 5 Years Ago (9), Mother Tongue (8), Age Groups (16) an...]

File Edit View Dimension Item Data Window Help

Sex

Geography: Denman Island Trust Area

Mother tongue		Total - Mother tongue			English			Fr...
Sex		Total - Sex	Male	Female	Total - Sex	Male	Female	Total
Age groups	Mobility 5							
	Total - Mobility status 5 years ago	1,070	540	530	830	420	415	
	Non-movers	710	335	380	545	255	290	
	Movers	360	210	150	285	165	120	
	Non-migrants	115	80	40	95	65	25	
	Migrants	240	125	115	190	100	95	
	Internal migrants	205	95	105	160	75	90	
	Intraprovincial migrants	140	60	75	120	55	70	
	Interprovincial migrants	70	35	30	45	25	20	
	External migrants	40	25	10	30	25	0	
5 to 9 years	Total - Mobility status 5 years ago	50	25	25	25	0	15	
	Non-movers	40	20	20	15	0	20	
	Movers	0	10	0	0	0	0	
	Non-migrants	0	0	0	0	0	0	
	Migrants	0	0	0	0	0	0	
	Internal migrants	0	0	0	0	0	0	
	Intraprovincial migrants	0	0	0	0	0	0	
	Interprovincial migrants	0	0	0	0	0	0	
External migrants	0	10	0	10	0	0		
10 to 14 years	Total - Mobility status 5 years ago	80	45	35	40	20	25	
	Non-movers	50	20	30	15	0	15	
	Movers	30	25	10	30	25	0	
	Non-migrants	25	15	0	25	20	0	
	Migrants	10	0	0	10	0	0	
	Internal migrants	0	10	0	10	0	0	
	Intraprovincial migrants	0	10	0	10	10	0	
	Interprovincial migrants	0	0	0	0	0	0	
External migrants	0	0	0	0	0	0		

For Help, press F1 3/3 Total - Sex ENG

start 2 Microsoft Excel Report Sep 03 2010... Document2 - Micros... ACT1 - [CONTACTS -... Beyond 20/20 Profe... 4:14 PM Monday 30/08/2010

B2020 allows you to create the exact table that you want. You can then export the table in to an Excel file.

Please be aware that the B2020 application has a Help section accessible from the main menu.